

# Installation of TCP/IP Printer in Windows XP Using the Printer's IP Address

Using the IP address of a printer is one way to set up a printer on your Windows XP computer. You will need to get the ip address of the printer; ask your friendly technical support person for help in getting this information.

1. Start → Settings → Printers.
2. Double-click on Add Printer & press Next.

3. Make sure that the Automatically detect and install my Plug and Play printer is NOT selected. Select Local Printer & press Next.
  4. If it for a printer with a newly designated IP address, select Create a new port & select Standard TCP/IP port from the type menu, and press Next.
  5. Type in the IP address of the printer & press OK.
  6. Select the manufacturer from the left pane & select the model of the printer from the right pane & press Next.
  7. Name the printer as you like & decide whether this printer is to be the default printer, and press Next.
  8. Decide whether to share the printer or not, and press Next.
  9. Decide whether to print a test page or not, and press Next.
  10. Press Finish to complete the installation.
- 

Revision #3

Created Mon, Aug 2, 2010 4:25 AM by McCann, Cathy

Updated Mon, Aug 2, 2010 4:29 AM by McCann, Cathy